- 1. Go to the Start Menu, All Programs, Microsoft Office and click on "Microsoft Outlook".
- 2. Once Outlook has loaded, click "Tools" on the top-menu and navigate to "Email Accounts..." (on some versions of Outlook this is labeled just "Accounts" or something similar.)



3. Select "View Or Change Existing Email Accounts" and click "Next >".



3a. Click "Add..." if you want to add an email. Click "Change..." if you want to change an existing email.

| E-mail Accounts | | | | |
|---|------------------------------------|----------------------|--|--|
| E-mail Accounts You can select an acc | count and change its settings or r | remove it. | | |
| Outlook processes e-mail fo | or these accounts in the following | g order: | | |
| Name | Туре | Change | | |
| mail.stantonstreetgroup. | com POP/SMTP | Add | | |
| | | Remove | | |
| | | Set as Default | | |
| | | Move Up | | |
| | | Move Down | | |
| Deliver new e-mail to the fo | ollowing location: | | | |
| Personal Folders | New Outlook | k Data File | | |
| | | | | |
| | | | | |
| | | < Back Finish Cancel | | |

4. Select "POP3" and click Next.

| E-mail Accounts | \mathbf{X} |
|---|--------------|
| Server Type You can choose the type of server your new e-mail account will work with. | s. |
| Microsoft Exchange Server Connect to an Exchange server to read e-mail, access public folders, and share documents. POP3 Connect to a POP3 or mail server to developed your or mail | |
| Connect to a POP3 e-mail server to download your e-mail. Image: | |
| Connect to an HTTP e-mail server such as Hotmail to download e-mail and synchronize mailbox folders. Additional Server Types Connect to another workgroup or 3rd-party mail server. | |
| | |
| < <u>B</u> ack <u>N</u> ext > | Cancel |

5. Fill in the information in the boxes as follows:

- Your Name: [Enter your first and last name in this box]
- E-Mail Address: [enter your E-mail address here, for example, jharrison@stantonstreetgroup.com]
- Pop-Server: [mail.domainname.com, for example, mail.stantonstreetgroup.com]
- SMTP-Server: [mail.domainname.com, for example, mail.stantonstreetgroup.com]
- Username: [my.email, for example, jharrison]
- Password: [Enter your password here]

6. Click "More Settings..."

| E-mail Accounts | | | | | |
|--|---|-----------------------------------|--------------------------------------|--|--|
| Internet E-mail Settings (POP3) Each of these settings are required to get your e-mail account working. | | | | | |
| User Informati | ion | Server Information | | | |
| Your Name: | Your Name | Incoming mail server (POP3): | mail.domainname.com | | |
| E-mail Address: | email@domainname.com | Outgoing mail server (SMTP): | mail.domainname.com | | |
| Logon Informa | tion | Test Settings | | | |
| User Name: | email | After filling out the information | on this screen, we | | |
| Password: | (*****) Your password | button below. (Requires netwo | ont by alcong the ork connection) | | |
| Log on using S Authentication | Remember password Secure Password n (SPA) | Test Account Settings | More Settings | | |
| | | | | | |
| | | < Back | | | |

6a. Under the "General" tab, "Mail Account", enter the server domain name, for example, mail.stantonstreetgroup.com

| Internet | E-mail Settings | × |
|---------------------------|---|---|
| General | Outgoing Server Connection Advanced | |
| Mail Acc Type accou | count • the name by which you would like to refer to this •unt. For example: "Work" or "Microsoft Mail Server" •stantonstreetgroup.com | |
| Other L | User Information | |
| Orgar | nization: | |
| Reply | y E-mail: | |
| | | |
| | | |
| | | |
| | | |
| | | |
| | | |
| | | |
| | OK Cancel | |

6b. Click the "Outgoing Server" tab

- Click the box next to "My outgoing server (SMTP) requires authentication". Make sure there is a check mark in the box.
- Click the circle next to "Log on to incoming mail server before sending mail". Make sure there is a dot in the circle.
- Click "OK"
- Click "Next >"

| Internet | E-mail Settings | ; | | | |
|------------|---|---------------|----------------------|--|--|
| General | Outgoing Server | Connection | Advanced | | |
| 💌 Му | My outgoing server (SMTP) requires authentication | | | | |
| OL | Use same settings as my incoming mail server | | | | |
| OL | og on using | | | | |
| L L | Jser Name: | | | | |
| F | Password: | | | | |
| | | Remember | password | | |
| [| Log on using Sec | ure Password: | Authentication (SPA) | | |
| <u></u> ΟL | • I og op to incoming mail server before sending mail | | | | |
| | | | - | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | OK Cancel | | |

7. Congratulations! Click "Finish".



