

How to Install Windows Mobile Device Center on Windows 10 Fall Creators Update

1. Assuming Windows 10 Fall Creators update is already installed, that all drivers for your device are installed.
2. [Install .NET 3.5](#)

<https://docs.microsoft.com/en-us/dotnet/framework/install/dotnet-35-windows-10>

3. Download Windows Mobile Device Center Installer

<https://support.microsoft.com/en-us/help/931937/description-of-windows-mobile-device-center>

Choose the correct version for your OS (64-bit or 32-bit).

4. Download "Pre-Installer"

<http://www.junipersys.com/content/download/13952/210444/file/wmdc-drivers-x64.msi>

<http://www.junipersys.com/content/download/13953/210449/file/wmdc-drivers-x86.msi>

5. Download WMDC-Helper.exe

<http://www.junipersys.com/Juniper-Systems-Rugged-Handheld-Computers/support/Downloads/Archer-models/Archer-2/WMDC-Helper-utility-for-Windows-10>

6. Install the "Pre-Installer"

Double click on either wmdc-drivers-x64.msi or wmdc-drivers-x32.msi

This will create c:\windows\windowsmobile\drivers with 4 folders inside.

7. Run the Windows Mobile Device Center Installer

Double click on either drvupdate-amd64.exe or drvupdate-x86.exe

You will need to wait at least 3 minutes. There is no window or any other visible activity – the installer will be working in the background. You can observe the process in Task Manager. Wait until:

- CPU utilization is close to 0%
- there is no drvupdate-xxxx.exe process
- there is only one msixexec.exe process

Now c:\windows\windowsmobile should contain the complete installation.

8. Run WMDC-Helper.exe to set needed registry settings

Note that it must be run as administrator.

9. Restart your computer

10. Open Windows Mobile Device Center (green window)

11. Connect your Windows Mobile device.